

Version 6.4

User Manual

© Copyright Inivis Limited 2008

Introduction	5
Welcome to AC3D	5
AC3D terminology	5
Vertex	5
Surface	5
Surface normal	5
	5
Group	5
Seleci-Moue	06 6
Texture	66
Texture coordinates	6
Bounding box	
Getting help	6
Windows/Views	7
Control nanel	
Toolbar	
View windows	7
Orthographic (2D) views	9
Navigating in 2D views	9
The grids	9
Using Background Images	9
3D views	
Navigating in 3D	
l aking a shapshot image	
Creating AC3D objects	12
AC3D Surfaces	12
Crease angles	
One-sided and I wo-sided surfaces	
Surface normals	
Polys/Polylings/Lings	۱۵ ۱ <i>۸</i>
Soheres hoves etc	
Naming objects	14
Lights	
Object mode lock	15
Creating other objects	15
Selecting, resizing, moving and rotating	16
Selecting	
Resizing	
Moving	17
Rotating	17
Extending/Negating the selection	
Clearing the selection	
Hiding objects	18 ۱۵
Model manipulation	19
Operations on objects	19
Texture	
Revolve	
Million	20 21
Douledii	ا ∠۲۱ 21
Optimize Surfaces	21 21
Reduce	21
Subdivide + / Subdivide -	
Commit subdivision	23
Re-centre	23
Minimum-centre	23
Fragment	23
Merge	24
Explode	
Extrude Along Path	24
Operations on surfaces	
Extruuring Flin normal	25 20
Change vertex order	20 າຂ
Flip Triangle Edge	
Divide	
Combine	29

Spine Indent Bowd		
indent Rovol	20	
Boyal		
Make hole		
Triangulate		
Soline	31	
- rut away object	31	
Demove outcoo only		
Remove surface only		
Calculate surface area		
Operations on Vertices		
Snap Together		
Snap Together by Distance		
Snap to Grid	32	
Shap Objects by Vertices	20	
Shap Objects by Venices		
Smooth Snape		
Align to Axis		
Weld		
Unweld		
Insert Vertex		
Divide Triangle Edge	.33	
Even via Educa		
Create Convex Surface/Object		
Create Ordered Surface		
Create Quad		
Create 2D Mesh		
Boolean operations	37	
Subtract		
Union		
Cut away		
Knife		
Knife and Cut Away		
Boolean examples		
Cutting a round-ended channel in a cylindrical object		
Cutting an alignon from a wing	40 10	
Cutting multiple windows from a fuselage		
Cutting a solid object at an angle	41	
Hints and Tips	43	
Subdivision Surface		
Subdivision Surfaces		
Subdivision Surfaces Changing the subdivision level		
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions	44 44 44	
SUDDIVISION SUITACES Changing the subdivision level Switching display of subdivisions Committing subdivisions	44 44 44 45	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples	44 44 44 45 45	
SUDDIVISION SUITACES Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tins	44 44 45 45	
Subdivision Surfaces. Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips		
Subdivision Surfaces. Changing the subdivision level Switching display of subdivisions. Committing subdivisions. Examples. Hints and tips. Using Extrude to add detail.		
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions?		
Subdivision Surfaces. Changing the subdivision level. Switching display of subdivisions. Committing subdivisions Examples. Hints and tips. Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level.		
SUDDIVISION SURfaces. Changing the subdivision level Switching display of subdivisions. Committing subdivisions Examples Hints and tips Using Extrude to add detail Display or hide subdivisions? Choosing the right subdivision level Advanced users.		
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users.	44 44 44 45 45 45 46 46 46 47 47 47	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing.	44 44 44 45 45 46 46 46 47 47 47 47 47 47	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture	44 44 44 45 45 46 46 46 47 47 47 47 47 47 48 48	
Subdivision Surfaces. Changing the subdivision level. Switching display of subdivisions. Committing subdivisions. Examples. Hints and tips. Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 48 48 48	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing. Setting a texture Changing the mapping. Changing the texture repeat and offsets	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 48 48 48 48 48 48	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 48 48 48 48	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools	44 44 45 45 46 46 47 47 47 47 47 47 47 47 47 47 47 47 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping. Changing the texture repeat and offsets Tools Model Information	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 48 48 48 48 50 50	
Subdivision Surfaces. Changing the subdivision level. Switching display of subdivisions. Committing subdivisions. Examples. Hints and tips. Using Extrude to add detail. Display or hide subdivisions?. Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping. Changing the texture repeat and offsets. Tools. Model Information	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 47 48 48 48 48 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render.	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 47 47 47 48 48 48 48 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render. Object Hierarchy.	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 47 50 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping. Changing the texture repeat and offsets Tools Model Information Render. Object Hierarchy. Object Property Editor.	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 47 48 48 48 50 50 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render. Object Hierarchy. Object Property Editor. Texture Coordinate Editor	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 47 47 47 47 47	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing. Setting a texture Changing the mapping Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy. Object Hierarchy. Object Property Editor Texture Coordinate Editor Selecting and manipulating.	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 47 47 47 47 47	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy. Object Hierarchy. Object Property Editor Texture Coordinate Editor Selecting and manipulating. Remapping the selection	44 44 44 45 45 46 46 46 46 46 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 51 53 53 53 54	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing. Setting a texture Changing the mapping. Changing the texture repeat and offsets Tools Model Information Render. Object Hierarchy. Object Property Editor. Texture Coordinate Editor Selecting and manipulating. Remapping the selection Render.	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 47 47 48 48 48 50 50 50 50 50 50 50 50 50 50 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Examples Hints and tips Using Extrude to add detail Display or hide subdivisions? Choosing the right subdivision level Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy Object Hierarchy Object Property Editor Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 47 47 47 47 47	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render. Object Hierarchy. Object Property Editor. Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator. Create Text	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 50 50 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail Display or hide subdivisions? Choosing the right subdivision level Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy Object Property Editor Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator Create Text	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 48 48 48 48 50 50 50 50 50 50 50 50 50 50 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy. Object Hierarchy Object Property Editor Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator Create Text Align Objects Position 3D cursor	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 47 47 47 47 47	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render. Object Property Editor Selecting and manipulating. Remapping the selection Replicator Create Text Align Objects. Position 3D cursor.	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 50 50 50 51 51 52 53 54 54 55 56 56 57	
Subdivision Suffaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing. Setting a texture Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy. Object Hierarchy Object Hierarchy Object Resolution Selecting and manipulating. Remapping the selection Replicator. Create Text Align Objects. Position 3D cursor.	44 44 44 45 45 46 46 46 46 46 47 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 50 50 50 50 50	
Subdivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy Object Property Editor Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator Create Text Align Objects Position 3D cursor	44 44 44 45 45 46 46 46 47 47 47 47 47 47 48 48 48 48 50 50 50 50 50 50 50 50 50 50 50 50 50	
Subdivision Suffaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Property Editor Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator Create Text Align Objects Position 3D cursor Materials The palette Editing Palette entries	44 44 44 44 45 46 46 47 47 48 48 50 51 52 53 54 56 56 56 56 57 57	
SUDDIVISION SUITACCES Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy. Object Hierarchy. Object Represent Editor Selecting and manipulating. Remapping the selection Replicator Create Text Align Objects Position 3D cursor. Materials The palette Editing Palette entries Loading and saving files	44 44 44 45 45 46 46 46 47 47 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 50 50 50 50 50	
Subclivision Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render. Object Hierarchy. Object Property Editor. Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator Create Text Align Objects Position 3D cursor Materials The palette. Editing Palette entries	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 50 50 50 50 50	
SUDDIVISION Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail Display or hide subdivisions? Choosing the right subdivision level Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy Object Hierarchy Object Property Editor Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator Solecting and manipulating Remapping the selection Replicator Solition 3D cursor Mosterials The palette Editing Palette entries Loading and saving files Importing other formats	44 44 44 45 45 46 46 46 47 47 47 47 47 47 48 48 48 48 50 50 50 50 50 50 50 50 50 50 50 50 50	
SUDDIVISION Surfaces Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users. Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render. Object Property Editor Texture Coordinate Editor Selecting and manipulating Remapping the selection Replicator Create Text Align Objects Position 3D cursor Materials The palette Editing Palette entries Loading and Saving files Importing other formats Triangle files		
SUDDIVISION SURFACES Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision? Choosing the subdivision? Choosing the subdivision? Choosing the subdivision level. Advanced users Texturing. Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy. Object Hierarchy. Object Hierarchy. Object Hierarchy. Object Hierarchy. Object Roperty Editor Selecting and manipulating. Remapping the selection Replicator Create Text. Align Objects. Position 3D cursor. Materials The palette. Editing Palette entries Loading and saving files Linporting other formats	44 44 44 45 45 46 46 46 46 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 50 50 50 50 50	
SUDDIVISION SURFACES Changing the subdivision level Switching display of subdivisions Committing subdivisions Examples Hints and tips Using Extrude to add detail. Display or hide subdivisions? Choosing the right subdivision level. Advanced users Texturing Setting a texture Changing the mapping Changing the texture repeat and offsets Tools Model Information Render Object Hierarchy. Object Hierarchy Object Property Editor Texture Coordinate Editor Selecting and manipulating. Remapping the selection Replicator Create Text Align Objects Position 3D cursor Materials The palette. Editing Palette entries Loading and saving files Importing other formats Triangle files Vector files Exporting files	44 44 44 45 45 45 46 46 46 47 47 47 47 47 47 47 47 47 50 50 50 50 50 50 50 50 50 50 50 50 50	

3D Studio (3ds)	
VRML 1	
VRML 2	
VRML2 Proto	
DIVE	59
MASSIVE	59
RENDERMAN	
POV-Ray	59
Trianale files	59
Object Library	
Rendering	60
A POV-Ray example	60
Annendix	62
3D Mauga gunnart	C2
SD Mouse support	
Performance tips	
Key-presses	63
Preferences/settings	64
Additional Information	65
Third party pluging	65
Owerful	
Greedle	

Introduction

Welcome to AC3D

AC3D is designed to make the construction of 3D objects fast and easy. It is used to create 3D models for simulations, games, rendering ray-traced images and for scientific and general data visualization.



AC3D runs on a wide range of standard hardware and is available across a number of popular platforms.

AC3D terminology

Vertex

A vertex is a single point in 3d space. It's specified by three coordinates x, y and z. More than one vertex can occupy the same position in 3d space. A vertex is always owned by a single object; they cannot be shared between objects. A vertex is usually part of one or more Surfaces, but need not be.

Surface

A surface in AC3D is a sequence of vertices. Surfaces are one of three types; polygons, lines or polygon outlines. The type of a surface defines how the surface is drawn and this can be easily changed. If a surface is set to be single-sided, it will only be visible from the front. Two-sided surfaces will be visible from both sides. It is more efficient to draw single sided surfaces and makes more sense when used as part of an object such as a sphere (where you can't see the other side of the surfaces). Surfaces have a material attribute, which defines the color and quality (for lighting purposes). Each vertex referenced in a surface has an associated Texture Coordinate. Vertices can be shared between surfaces in the same object.

Surface normal

A 'surface normal' specifies the direction a surface is facing. Normals are used in lighting calculations. Surface normals are automatically calculated by AC3D. A surface is defined as facing the viewer if the vertices can be seen in an anti-clockwise direction.

Object

An AC3D object is a list of vertices, and surfaces that use these vertices. It also has other attributes such as a name and texture.

Group

A group is a special object that has no surfaces or vertices but has other objects as children. Groups are created by selecting two or more objects and selecting 'Group' from the edit menu or toolbar. Use the 'Ungroup' function to separate the objects.

Select-mode

The select mode allows control over the level of editing in AC3D. In 'Vertex', individual vertices can be selected and adjusted. In 'Surface', operations are performed on one or more selected surface. In 'Object', whole objects are selectable. This allows manipulation of objects, even if they are part of groups. In 'Group', selecting all or part of an object automatically selects the top level object.

Material

A material defines the color of a surface and also the attributes that define the way it will react to light e.g. shininess.

Texture

Graphical images can be mapped onto the surfaces of an object. The images are usually from graphics files such as gif, jpg, bmp etc.

Texture coordinates

When the vertex of a surface is drawn, a texture coordinate specifies the position of a texture image to map to that point. A texture coordinate is a two dimensional (u,v) value which defines the point on the 2D image.

Bounding box

When you make a selection of objects, surfaces or vertices, a green box outlines it. You can drag, resize or rotate this box to adjust the contents

Getting help



User interface components in AC3D have 'balloon help'. Small 'tooltip' windows will popup when the mouse pointer rests over a button or field label.

This feature can be switched off from File->Settings.

When browsing through the menu items, the function on each item is described in the message text at the bottom of the AC3D window.

Windows/Views

AC3D has a control panel on the left, plus 4 view windows. There's also the menu and toolbar at the top and an information bar along the bottom.

Control panel



This is where the main controls over the selection and draw modes are located. It also contains the surface-type controls, the palette of materials and the object name field.

The top of the control panel shows information about the current selection. When the mouse is being used to interact with models, this area will also display current positions, distances moved and other related information.

Toolbar

This contains buttons for some of the most commonly used functions.

All None Dup Cut Copy Pa	stel Group Ungroup Flip: X Y Z 50% 200% -10% +10% Subdiv + Subdiv -	<u>• • • , , , , , , , , , , , , , , , , ,</u>
All	select everything	
None	clear the selection	
Dup	duplicate the selection	
Cut/Copy/Paste	use AC3D's internal clipboard	
Group/Ungroup	put selected objects into a group/remove the group object	
Flip x/y/z	flip the section about this axis	
200%/50%/+10%/-10%	scale the selection uniformly	
10 10 10 10 10 10 10 10 10 10 10 10 10 1	Maximize a single view or view ALL together	

View windows

By default, AC3D starts with three two-dimensional (2D orthographic) view windows and a single three-dimensional (3D) window. The default view windows show Front, Left, Top and 3D camera angles onto the model space.



The dividers between the 4 view windows can be dragged to resize the views. Individual views are maximized by clicking on the view buttons at the top right of the main window (alternatively, the F1-F5 keys can be pressed to switch between the different view configurations).

The main window size/position and other settings are saved when AC3D exits.

	front		left	12
AC3D default	top	*	3d	

The configuration of the views that AC3D starts up with can easily be changed from the menu Views->Configure views.

Each view window has an individual menu at the top. This contains the menu for the view angle (Camera), changing the viewpoint (e.g. focusing on the currently selected area) and some misc. controls that are dependent on whether the window is set to 2D or 3D.

Camera View 3D

🚓 🗧 📩 🏓 🚛

The Camera angle can be changed at any time. This is useful if, for example, you need to view (or work on) a model from the underside (bottom view).

The icons on the right of each view-menu allow you to use the mouse to navigate around the 3D space, show a clean image, and maximize the view window.

\$	Spin (3D views only) – press and drag
*	Move/Pan view- press and drag
\$	Zoom in/out view – press and drag
A	Inspect – Switch to show clean image (display without all surface outlines, grid, controls etc) and change to simple navigation mode.
	Maximize/minimize view button

The spin, move/pan and zoom button are special controls that are held down (left mouse button) whilst the mouse is dragged. The views adjust their viewpoint as the mouse is dragged.

Additional views can be created from the menu Views->New-View.



Unlike 2D CAD programs, the space presented in the AC3D view windows is not like a finite piece of paper which has a limit and edges. You can move viewpoints just like a person moves around in real 3D space. There are no real edges to the available space (apart from reaching computational limits).

Orthographic (2D) views

When a view camera is set to Front, Back, Top, Bottom, Left or Right, the view is non-perspective orthographic 2D.

An orthographic view shows a view parallel to a single axis.

The items on the main 'Orth' menu control how views set to these camera modes are drawn and what components are visible. For these settings, all Orth windows work together e.g. switching from filled to wireframe appearance in one Orth window causes all other Orth windows to also be set to wireframe.

Although it's useful sometimes to work in a single view, seeing all the windows at once can be very helpful when positioning objects and laying out scenes.

Navigating in 2D views

Use the mouse to pan or zoom an orth view. The keyboard arrow keys pan and control+up/down zooms in and out. Holding down a shift key increases the movement/zoom distance.

The grids

In the orthographic windows there are two grids - the draw grid (major lines) and the snap grid (minor lines). Both can be set from 'File->Settings' and their display can be toggled on/off by selecting 'Grid' from the Orth menu (or pressing the 'g' key when focused in an orth window).

The Snap grid is shown by thin visual guide lines; the draw grid uses thicker lines. If 'Gridsnap' is switched on, moving/resizing/creating mouse movements will be aligned to the nearest snap grid points.

The grids can be configured to display units of any size e.g. for eighths of an inch, the major draw grid would be set to 1.0 and the snap grid set to 0.125 (1/8th).

Using Background Images

Any orthographic (2D) window can display a background image. This can be useful for tracing shapes or laying out objects in relation to a scanned image e.g. a plan or map. Background images are set and unset from the Orth menu at the top of an orthographic window. All image formats that are supported by AC3D's texture loaders can be used as background images.



Background images will scale and move with the views. By default the image will be centered on the origin. The scale and position of the background image is adjusted by using alt and the cursor keys. Alt and the cursor keys reposition the image, whilst Alt+Shift plus cursor up/down scale the image.

Details of background images are currently not saved with models or when AC3D exits.

3D views



A 3D view window displays the current model in a three dimensional perspective and changes instantly when any modifications are made to the current model.

The main 3D menu (at the top of the main AC3D window) contains controls to switch visibility of many attributes within the 3D window. Changing these controls affects all 3D windows within the program.

A 3d grid is available - toggle with 'g'. The grid lies on the XZ plane (floor).

'w' toggles between wireframe and filled drawing, 't' toggles textures. 'l' toggles the fixed light. See the 3D menu for more viewing options.

Navigating in 3D

Two navigation modes are available in this window – 'spin' and 'walk'. These can be switched from the view's own 3D menu or by pressing the '1' or '2' keys whilst the pointer is in the 3D window.

Spin mode

Button controls at top of view for spin, pan and zoom

From keyboard:

Spin- up/down/left/right keys, or Alt+left mouse button Zoom – Control+up/down

Walk mode

Button controls at top of view for walk/fly, pan and tilt

From keyboard: Move forward - up-key Move backward - down-key Turn - left/right keys Move up/down – alt+up/down

Holding down the shift key with the above combinations increases the distance of travel $% \left({{{\rm{A}}_{\rm{B}}}} \right)$

Taking a snapshot image

Camera View 3D
Front
Back
Left
Right
Тор
Bottom
✔ 3D
Copy Image to Windows Clipboard
Copy Image to Windows Clipboard

Windows and Mac users can quickly copy the image shown in a view to the system clipboard by selecting the item on the Camera menu, which is on each View window.

After selection of this menu item, you may switch to another program e.g. an image editor or word processor program and then 'Edit->Paste' within that in order to insert the image

The same function is also available on the Edit menu (for the main 3D view). Note that the 'Copy' item on the Edit menu is used for the internal AC3D clipboard, the item that copies the image to the system must be used to retrieve the image.

To increase the quality of the image, anti-aliasing can be switched on (from the view's 3D menu). This 'smooths' the image. Anti-aliasing slows down rendering of the 3D image so it's recommended that it only be used when preparing images for a snapshot.

Inspect mode

Þ

Pressing down the eye icon, which is available on each view, sets the view into Inspect mode. Inspect mode switches off the display of vertices, surface outlines etc so that a 'clean' image is displayed. It also changes the way that you can navigate the view. When inspect mode is on, simply dragging the mouse navigates (normally the alt key would be used).

Inspect mode is useful if you are performing a lot of work in the other views and using one view for previewing the changes. It's also useful with additional monitors, where one monitor has a single AC3D view (Views->New-View) that is set to inspect. Work can be performed on the main monitor and inspected (quickly spin or walk) on the other monitor.

Creating AC3D objects

AC3D Surfaces



Set Surface type					
Poly	Polyline Line				
Smooth	1	Flat	1	S	25

Objects in AC3D consist of a collection of vertices and a number of surfaces that reference those vertices. A surface may be one of three types: Polygon, Polyline or Line. A polygon is a filled area, a Polyline is a wire-frame outline of the polygon (a loop that joins the start vertex to the end), and a Line has a specific start and end.

Surface type is changed by pressing a button on the control panel. The Surface type buttons are located at the bottom of the control panel (Poly, Polyline, Line):

This panel also contains controls to set surfaces to be smooth or flat This determines the way that a polygon is drawn (it has no effect on Lines or Polylines).



If a surface is flat-shaded, the color across the surface will be constant. If it is shaded then the color will be 'graded' depending on lighting conditions.

Vertices can be shared between surfaces (i.e. one or more surfaces use the same vertex). If these surface types are set to 'smooth', the effect is of one continuous 'smooth' surface. The vertices MUST be shared for two surfaces to be smoothed together. This method of shading allows smooth- looking objects to be created from relatively simple shapes.

Crease angles

Each AC3D object has a crease-angle property. This is adjusted via the Tools->Object Property Editor. The crease angle is specified in degrees and is used to determine if adjacent surfaces in the object should be 'smoothed together' by averaging the surface-normals. The angle between adjacent surfaces is measured and if this is larger than the crease angle the surfaces will be smoothed.

A crease angle of zero degrees forces all surfaces to be flat. A crease angle of 180 degrees forces all surfaces to be drawn smooth.

Setting a surface type to 'flat' forces the surfaces to remain flat shaded. Setting a surface type to smooth allows it to be under control of the crease angle.

Example: a cylinder with all surfaces set to 'Smooth'.

crease angle = 0°

All surfaces appear flat.



= 45°



The cylinder edges are 'smoothed together' but the end is flat because the angle between it and the edges is > 45°



Crease angle = 91°

The cylinder sides are now shaded along with the edges.

One-sided and Two-sided surfaces

The '1S' and '2S' buttons select how many sides a surface has (one-sided or two-sided). If a surface is single sided, it will only be visible from one side. The following pictures demonstrate this:



In this model, there are three objects - a green rectangle, a red rectangle and a blue ellipse (made by creating an ellipse object and setting the surface type to be 'Poly').

The red rectangle has been set to be single-sided '1S'. This means that it is visible from the 'front' but not from the back (the second image shows the whole model rotated).

Objects such as spheres and cubes, which do not have any interior surfaces visible, benefit from a speed optimization when being drawn with the surfaces single-sided.

Surface normals

The direction a surface is facing is determined by its 'Normal' (indicated by arrows in the above diagram). This is a 3D graphics term for a line at right angles to the surface that indicates a direction). Normals are used to calculate surface colors and shading when the objects in AC3D are drawn. For smooth shading, vertex normals are automatically calculated by averaging normals of all connected surfaces.

Normals can be visualized in both the orthographic and 3d views ('Normals' on the 'orth' and '3d' menus). This preview is useful for solving problems where, for example, some surfaces in an object are the wrong way around. This can cause surfaces to appear missing if they are one-sided, or the smoothing can appear uneven. Viewing the normals is also handy for use with the extrude function and can help determine the extrude settings that ensure that new surfaces face in the correct direction.



This picture shows two spheres. The sphere on the left shows correct normals (i.e. all facing outwards). The sphere on the right shows some surfaces facing in the wrong direction. Notice how the shading is not consistent.

AC3D automatically calculates the normals (both surface and vertex).

To flip the direction of a surface, use Surface->Flip Normal. (This actually reverses the order of the vertices in the surface so that the automatically generated normal faces the opposite way).



The AC3D control panel contains a number of 2D and 3D object shapes that can be created.

New objects are created by selecting one of these buttons and clicking/dragging in one of the view windows.

Polys/Polylines/Lines



To create a Poly/Polyline/Line, click to position each point and either doubleclick or press the middle or right mouse button to end. The surface type can be altered later from the control panel if you need a different type.

These objects consist of a list of vertices and a single surface. The surfaces from more than one of these objects can be collected together into a single object by using the Object->Merge function.

Polygons should be 3 or more points. Concave polygons are handled by AC3D. They can be converted to triangles by using the Surface->Triangulate function.

It is possible to draw a line or poly in different windows - creating a non-planar surface. This makes sense with lines but is not correct for a polygon which should have all of the points on the same plane. Invalid polygons i.e. polygons that have less than three vertices are displayed in a cyan color. Surfaces that have crossing edges are displayed in a red color.



This shows part of a sphere where some vertices have been deleted. Polygon surfaces with only 2 vertices have been left. These can be removed by using Object->Optimize Surfaces.



This shows a four point polygon where the vertices are positioned so that the edges overlap. This is fixed by moving the vertices.

To draw shapes that have vertices in the same position as an existing shape, use the 'Nearsnap' function; the control for which appears under the draw mode section when /Poly/Polyline/Line mode is selected. When Nearsnap is on, the next point drawn will 'snap' to the nearest existing vertex (when there is a vertex within a certain range).



Creating a 3D object by dragging the mouse in a window specifies two of the dimensions for the new object - the third dimension is an average of the original two. The location of the object in the third dimension is specified by the 3D cursor.

These objects can also be created with a single click in a view window. This will create a regular object that fits into a $1 \times 1 \times 1$ square.

The 3D cursor is shown in the orthographic views by a cross. This is repositioned by using the tool, Tools->Position-3D-Cursor. Most people rarely use this because it is very easy to create an object and position it afterwards.



Some object types allow parameters to be set before creating the object. For example, spheres and meshes can be made from triangles or quads.

Controls for any available parameters appear in the panel underneath the Mode box on the control panel.

Naming objects

When created, AC3D Objects are automatically named. The object name box is at the bottom of the control panel and allows these names to be set.

Object names can only be edited/set in Group or Object select mode. Object names need not be unique and can be the same across multiple objects. This can be useful for selecting or finding particular objects with the Edit->Select-by-name function (e.g. to select all objects named 'chair'). Object names are used in some of the file formats exported by AC3D.

If AC3D is being used to generate VRML or Dive files, URLs and other text can be associated with objects. This text is used in a number of the export file formats that AC3D generates. The names, text and URLs are saved in the .ac AC3D files. Text attached to each object is entered into the field on the Tools->Object Property Editor window. Object names can also be set in the property editor.

Lights

Lights have no associated geometry and represent a 'point light'. In the AC3D views, lights are represented by this symbol:



Lights are fixed brightness white lights. Lights are selected and repositioned in Group or Object select mode. Lights are generated in exported files such as POV and RIB files. The generated files can be edited to alter the lighting attributes.



This image shows a green sphere with two lights (indicated by white spheres) - the main headlight is off. (The headlight in the 3D window is toggled on and off with the 'I' key, or from the main '3D' menu).

If the headlight is on when POV or RIB files are generated, a light will be added to information in the file.

Object mode lock



Clicking twice on an object mode button causes the mode to 'lock'. This is indicated by the button changing to green. When a mode is locked, the mode does not revert to Move/size after an object is created. Pressing Move/Size, Rotate (or extrude) releases the lock.

Creating other objects

It is very easy to create other objects from these shapes. For example, to make a torus shape ('donut'), create an ellipse and select Object->Revolve.

A cone can be made in a number of ways. Create a cylinder; select one end (in vertex mode) and select Vertex->Snap Together. A cone made this way will have the texture coordinates set correctly. For a simpler cone (fewer vertices), optimize the vertices with Object->Optimize Vertices. This means that the centre-point of the cone will be a single vertex which is shared with all the sides. Some other ways of making cones include making a 'disk' and pulling the centre point up or using Object->Revolve to revolve a line around an axis.

'Extrude' is used to add extra parts to objects or to give 2d shapes depth. Objects can be cut into pieces and specific surfaces deleted.

Selecting, resizing, moving and rotating

In AC3D, the manipulation of 3D objects works in a very similar way to a 2D drawing program i.e. the selection is shown highlighted and 'handles' can be moved to reshape the section.



Selected components (surface, vertices) are shown in a different color and are surrounded by a 'bounding box' (usually green).

Selection is possible in move/size, rotate and extrude modes. The default mode is move/size.

Selecting



The Select-mode defines the granularity of selection i.e. it determines if selections will affect objects, groups or vertices. To select in AC3D, either click the left mouse button or use the left mouse button to drag a box over an area. When something is selected, the bounding-box that appears can be dragged or resized, directly affecting the points/surfaces/objects.

	Vertex mode	vertices can be selected by a single click on a single vertex or by dragging a box over a number of vertices
	Surface-mode	a single surface is selected by a click . Multiple surfaces are selected by dragging a box over an area
Ó	Object-mode	selecting any part of an object causes the whole object to be selected
8	Group-mode	a group of objects can be selected by highlighting any part of a single object that belongs to a group

There is an important difference between a click-select and a drag -select. Click-selects are used for selecting single entities e.g. one object, one surface, one vertex. A click- select will select the nearest entity underneath the pointer. A drag-select will select everything within the drawn box that lies underneath the region. Click-select is useful, for example, when selecting a single surface of a sphere (where a drag -select will always select more than one surface).

Selections are preserved between changes of select modes. Changing from vertex to surface select-mode means that any surfaces that have all vertices selected will remain selected in surface-mode.

Resizing



Dragging the 'handles' at the corners of the bounding box, using the left mouse-button, resizes the selection.

Holding down the control key whilst dragging an edge handle resizes opposite edges. On the corner handles, holding down the control key scales the selection uniformly.

Resize selections of vertices and surfaces



It is possible to resize a selection down to zero width/height. This is useful for lining up vertices.



Moving



The green bounding box is dragged with the left mouse button to reposition the selection.

Holding the control key down whilst dragging, constrains movement to up/down or left/right only.

In a 3D view, AC3D displays green arrows on each side of the bounding box. These can be dragged to move the selection.

Rotating



When the rotate button is selected, clicking on the bounding box and dragging left/right will rotate the selection about the point of the first click.

Extending/Negating the selection

Holding down the shift key whilst selecting with the left mouse button extends the selection (adds new entities). Pressing shift whilst selecting with the 2nd (or 3rd) mouse button negates (subtracts) items from the current selection.

Extend and negate selection work in all select modes.



This picture shows the top and bottom of a sphere selected. This is done by first selecting the top vertices with a drag, then holding down the shift key and dragging across the bottom of the sphere.

Clearing the selection

Clicking outside the area of the bounding box will cause everything to become unselected. The selection can also be cleared by pressing the 'None' button in the toolbar or from the menu Edit->Select Nothing.

Hiding objects

Hide: Sel Unsel None

Hiding allows objects to be temporarily removed from the views. The current selection, or objects that are not selected, can be hidden from view. The 'Unhide' button ensures that all objects are visible. The 'Show Hidden' toggle in the main 3D menu determines if the hidden objects are visible in 3d views. Hiding is useful when access is needed to work on obscured objects.

Locking objects

Lock: Sel Unsel None

Locking is useful for temporarily disabling objects that are obscuring others. When objects are locked, it's not possible to select them.

Locking also helps with the speed performance when editing large models. It works in a similar way to hiding, except that locked objects are drawn in grey wireframe.

Note that if objects are hidden (or locked) and the model is saved/exported, hidden and locked objects are included in the file.

Model manipulation

Operations on objects

These operations are on the 'Object' menu and act upon one or more selected objects.

Texture

Each object can have one texture. A texture is a 2D bitmap image, such as a .gif or .jpg file, which is drawn onto the surfaces of an object.

To set a texture on an object, use Object->texture->Load texture. AC3D's default palette of objects predefine the way that the textures are mapped onto the object surface. To adjust this, or to define a custom mapping, use AC3D's Texture Coordinate Editor (Tools menu). See the section on 'Texturing'.

Revolve

Revolving makes copies of the selected objects, rotating each copy, and then creating surfaces between the copies. It's recommended that this function be used to revolve 2D outlines of shapes rather than filled-polygon objects. Any revolved line objects are automatically removed after the revolution. The axis around which the revolution is performed can be altered.



To create a torus - make a circle in the Front window:

Select 'Object->Revolve...'

🔥 revolve	8
degrees:	360
axis:	Y 🔟
segments:	12
offset:	0.0
Revolve	Cancel

Set the axis to Y and click Revolve. You should see something like this:







Select the 'smooth' surface type (near the bottom of the control panel) to make it appear rounded

The degrees of revolution can also be altered- e.g. 270 degrees:

If there are points that need to be in the centre of the final revolved object - (e.g. the start and end points of the cup profile above) then these points should lie exactly on the axis. Drawing the line with 'Gridsnap' can ensure this. Alternatively, snapping the points to the grid (Vertex->Snap to Grid) or by using the control panel Move-to function to ensure that two of the values are zero. If these points are not exactly on the axis a small hole or possibly overlapping surfaces will be created. If this happens, the 'Vertex->Snap Together' function and Object->Optimize Vertices can be used to remove duplicate points.

Setting the revolve offset allows the profile to be moved along an axis for each revolution. This is useful for making spiral pipes, springs and screw threads.

> revolve degrees: 3600 axis:

segments: 120

Example: creating a spring:



Example: creating a thread



offset:	1.25
Revolve	Cancel
nevorve	Cancel
All and the second	-

3600

Y

240

1.0

Cancel

degrees:

axis:

segments:

offset Revolve Y.



Mirror

The mirror function duplicates all object surfaces and vertices and flips the new surfaces and vertices around the specified axis. Examples:

A hemisphere





Object->Mirror-> -X

Object->Mirror-> +X



Object->Mirror-> X axis



Where possible, Mirror will remove duplicate vertices. If mirroring half of a shape, use Vertex->Align to Axis to align the inner edge vertices to an axis. Alternatively, select the inner vertices and resize one dimension to zero – this flattens the selection, aligning the vertices.

Mirror is useful after use of the AC3D real-time Mirror function (View menu) where half of a symmetrical object has been worked on.

Boolean

Boolean operations allow objects to be cut and intersected with one another. See the chapter dedicated to Booleans.

Optimize Vertices

This function removes duplicate vertices from each selected object. For vertices to be removed an object must own the vertices and they much match the same position exactly. The function will share one vertex between each connected point. This can make the object less complex and means that vertex normals can be calculated if smooth shading is required. This function also removes duplicate vertex references from the surface - something that might cause a bad polygon. If vertices do not match the same position, Vertex->Snap Together or Vertex->Snap Together by Distance can be used to move them to the same point.

Optimize Surfaces

This function removes any duplicate surfaces and any polygons that consist of 1 or 2 vertices (these may exist if vertices have been deleted from an object). AC3D highlights invalid polygons by displaying them as cyan lines.

Reduce

This function reduces the number of vertices (and polygons) whilst trying to retain as much of an object's original shape as possible. This is useful for saving on storage space and for speeding up the rendering of complicated objects. This function can be used to create different objects that will be shown at different distances (LOD – level of detail). For example, a car object should be viewed close up with all polygons, but from a distance a more simple shape is adequate and can save drawing time.

Reduce		×		
Reduce number of vertices to %: 90				
☐ keep original object/s?				
Reduce		Close		

A target percentage specifies the proportion of vertices that are to remain. For example, if an object has 100 vertices and "80%" is entered, the final object will contain 80 vertices.

The original object can remain in the model, or it can be replaced with the new object. If the original object is kept, the new object will be created in the same position and will be selected.

An example:





Reduced to 40% gives:





276 surfaces, 150 vertices: a saving of 456 polygons.



The reduce window remains visible so that different reductions can be tried (use Edit->Undo to revert to the previous state).

Subdivide + / Subdivide -

These functions change the subdivision level. A surface subdivision is where each surface is divided, and then the shape of the overall object is 'smoothed'.

Original object







Two subdivisions



Three subdivisions



without surfaces displayed:



Commit subdivision

This function affects objects that have the subdivision preview level set to a value larger than zero. The subdivision preview level is set from Tools->Object Property Editor or by adjusting the subdivision level from Object->Subdivide +/- (also from the toolbar controls).

It converts the subdivision preview into real polygons for the selected objects.

See the section on 'Subdivision surfaces' for more information.

Re-centre

Object centres define the 'local origin' of AC3D objects. Object centres can be seen by switching on the '+' button on the main Orth menu. This function sets this origin at the centre of gravity. This can be useful for specifying where the pivot points or local-origin of an object are.

Minimum-centre

This function sets the object-centre (object's origin) to the minimum xyz of the object.

Fragment

Fragment creates one object per surface of the original object so that each object contains only one surface and the necessary vertices. The surfaces are no longer 'smoothed' together - this is because each surface is now a separate

object and vertices cannot be shared across objects. If you need to extract a number of surfaces from an object, using Surface->Cut Away Object is recommended.

Merge

This function places all of the surfaces from the selected objects into one single object. This does not optimize the vertices so that they can be shared across the surfaces. Use menu Object->Optimize Vertices after merging to create a more efficient object and/or get smooth shading across adjacent surfaces.

Explode

This is similar to fragment, but each new object is moved forward in the direction the surface is facing by a specified amount.

Extrude Along Path

This function 'sweeps' a profile along a specified path to create a 3D shape. The operation works on two objects: the profile and the path. The order in which these objects are selected is important. The profile should be selected first and the path second (usually with shift-select). An example:



Ensuring that the select mode is Object, first select the circle, then hold down the shift key and select the line. Next select Object->Extrude Along Path:



The shapes created by this function can easily be smoothed by using AC3D's subdivision. In the following image, the line has been subdivided twice, smoothing the appearance. It is possible to reposition the vertices in this line to fine-tune the desired shape. After using Extrude Along Path, the new object initially appears the same as before but once subdivided, has the same smooth profile as the original line/path.



Operations on surfaces

Extruding



Pressing the extrude button on the control panel (or pressing the 'e' key) when there are one or more surfaces selected enables the function. The actual extrude is done after the selection is dragged.

Extruding is a powerful function that can be used for a number of tasks. It works by making new surfaces at the edges of the current selection. The original selection can be removed and/or copied to the end of the new surfaces.



Selecting one or more surfaces and then selecting the extrude button on the control panel brings up the extrude parameters.

Here the number of sections to produce is specified. The end of the new object can be capped with a copy of the original selection. New surfaces can have their normals reversed. Removal of the original surfaces is also an option.

After setting these parameters, the bounding box is dragged in the desired direction. If the control key is held down, movements of the mouse are constrained to either horizontal or vertical.

The extrude function is best demonstrated with some examples. This star was made by creating a 10-sided disk, selecting alternate vertices and shrinking the selection, using the -10% toolbar button a few times.



The magenta lines shown here represent the normals. Normals can be displayed by switching on 'Normals' from the Orth and 3D menus. Displaying the normals is used here to help determine the direction in which to extrude the object. In the extrusion, if the selection is dragged in the same direction as the normals, the resulting shape will hide the front of the original surfaces. This is useful if one side of a box is being extended, but in this case the original surfaces need to be facing outside of the final shape. This means that the surfaces need to be dragged in the opposite direction to the normals. Here, 'flip new surfaces' is used so that all the new surfaces face outwards.

This is what happens when the selection is dragged up in the plan window:



If 'remove original' was ticked then the star that that is being dragged will be deleted:



Here, the original surfaces have been removed to leave a star-shaped box (without a lid). If 'cap end' had been unticked, then it would have been possible to see right through the star shape.



This picture shows what happens when 'sections' is set to 4.

To extend an existing set of surfaces, it may not be desirable to keep the existing surfaces inside the new object.

Here is a cube that has had a single 'Surface->Divide'. Two of the surfaces are selected.



These surfaces can be extended without keeping the original surfaces (since they will not be visible as they are inside the shape.)

These settings are used:



To perform the extrusion, the bounding box is dragged to the left (in either the front or plan window). Holding down the Control-key whilst dragging ensures that the new surfaces are square to the original. This gives:



When extruding lines, ensure that Remove original is ticked and Cap end is un-ticked. This ensures that no lines remain in the new surfaces.





It is useful to switch on the display of normals when extruding to check that the resultant surfaces are facing in the correct direction. If they are not, select the surfaces and use Surface->Flip Normal.

Flip normal

This effectively reverses the list of the vertices in each selected surface. This reverses the way that a poly 'faces'. A polygon is defined as 'facing' if the vertices appear anti-clockwise to the viewer. If a polygon is set to be one-sided (by pressing the '1S' button on the control panel) then it will only be viewable from one direction - the direction it is facing. The display of normals can be switched on in the orth and 3D windows – this can help determine if any surfaces are facing in undesired directions.

Change vertex order

This changes the order in which the vertices of a surface are drawn, by moving the first vertex to the end of the vertex list. This can be used to change the position of a break in a line. It can also be used to fix a bad polygon, which has the first three vertices in a non anti-clockwise order - causing the normal (used for lighting) to be

incorrectly calculated. If a polygon appears all black, this function may need executing (possibly repeatedly) until it appears correctly.

Flip Triangle Edge

Given two adjacent triangles, the joining edge is flipped:





Divide

Divide creates new surfaces by splitting each surface to make quads (four point/four sided surfaces)



Note that because this function splits surface edges, it affects any surfaces that are adjacent to those being divided.

This image shows a box that has had the top surface divided. The red surfaces that are adjacent now have five points each because the division inserted an extra vertex.



Combine

Combine takes two or more adjacent surfaces and creates a single surface.

The selected surface must share edges for this function to complete. Select the menu item or press the 'c' key to execute the function.



two surfaces selected



after combine - one surface

It is possible to combine surfaces that do not lie on the same plane. It is recommended that the vertices be flattened in order to make them lie on the same plane.

If after combining surfaces, the new surface appears black from every angle, this means that the first three vertices of the surface form an angle of more than 180 degrees. To prevent this, the vertex order must be changed (Surface->Change Vertex Order) so that the first three vertices of the surface form an angle less than 180 degrees.

Flatten



This acts on multiple surfaces and aligns the vertices so that they all lie on the same plane.

Spike



This creates a 'spike' in place of each surface selected. The distance that the apex of the spike will be away from the original surface is specified.

If used with a spike distance of zero, this function is useful for breaking a surface into triangles around a central vertex.



Indent

This function creates new surfaces around the edge of existing surfaces.





If the select mode is Surface or Vertex, the new 'centre' surface (or vertices of it) is selected after the operation completes.

Bevel

Beveling a surface does the same as Indent but the new centre surface is raised. Two parameters are required; one for the distance in from the edge, the other is the distance to move the new (inner) surface forward.



If the select mode is Surface or Vertex, the new 'centre' surface is selected after the operation is complete.

Make hole

This function creates a hole in each selected surface.



This image shows 4 objects that have had holes made in them - An ellipse (set to poly surface-type), a sphere, a cube and a disk. Notice how the insides of the sphere and cube are not visible through the holes- this is because the default surfaces for these objects are singlesided and face outwards. To see the insides though the holes, these surfaces need to be made two-sided by pressing '2S' on the control panel.

Some concave polygons may have overlapping surfaces after making holes. Vertices may need adjustment to prevent overlapping.

The size of the hole is specified as a percentage and can be adjusted in File->Settings.

Triangulate

This splits non-triangles (i.e. polygons with more than 3 sides) into more surfaces, each new surface being a triangle. This operation can fail if it is given a 'bad' polygon - i.e. one that has overlapping edges or duplicate vertices.



Spline

This is useful for smoothing out a 'line' object and for rounding off polygons. New points are interpolated between existing points.





Cut away object



This function takes all of the selected surfaces and vertices and puts them into a new object. This can be useful for extracting parts of objects e.g. splitting a sphere into two.

Remove surface only

This deletes any whole surfaces selected. The vertices will remain.

Calculate surface area

This function calculates the total surface area of the selected surfaces. Note that the total area accounts for one side of each surface.

Operations on Vertices

The majority of functions on the Vertex menu are available when the Surface or Vertex select mode is active and one or more vertices are selected.

Snap Together

This sets all selected vertices to the same location. The vertices can be in separate objects or the same object. The point that they are snapped to is the average of all selected points.

Snap Together by Distance

This function moves vertices together that lie within the specified distance. This is useful, for example, to join two halves of an object together.



This picture shows a close-up of an object where two halves have been positioned together. Notice that there is a visible seam along the top. This is because the two halves are separate objects. Once the two halves have been merged together into a single object (Object->Merge), the vertices need to be shared in order for this seam to disappear.

If Object->Optimize Vertices does not remove duplicate vertices then it means that the vertices are in very slightly different positions. The solution is to select the vertices along the join and Vertex->Snap Together by Distance. The Object->Optimize Vertices will remove the duplicate vertices and allow the surface to appear smooth.



Snap to Grid

This moves each selected vertex to the nearest grid position. This may or may not be the visible grid. The snap grid is defined by 'snap grid' in settings and may be different to the 'draw grid' (which is the visible grid).

Snap Objects by Vertices

One vertex in each of two separate objects should be selected before executing this function. The objects will be moved together so that the two selected vertices are in the same location.

Smooth Shape

This function repositions the selected vertices in order to smooth the shape of the surfaces.

Align to Axis

This function moves all selected vertices so that they lie on the specified axis.

Weld

Weld removes duplicate vertices where more than one vertices lie in the same position.

Unweld

This creates new vertices so that each surface will access a unique vertex in the same object. New vertices will be created in the same location as the originals.

Insert Vertex

This function inserts a new vertex between each selected pair of vertices. Insert Vertex is useful for adding extra points into a line.

If the two vertices selected are on an edge which is shared by two or more surfaces, only one vertex will be created, but it will be shared across the surfaces.

Divide Triangle Edge

This function takes two selected vertices and divides the edge between two triangles. This splits each triangle into two further triangles.



two vertices selected



after the edge division

Extrude Edges

This function provides a quick way of performing a simple extrude on one or more surface edges (i.e. between vertices).



Vertices selected.



After Vertex->Extrude Edges, the new surfaces and vertices have been created but are not fully visible until moved.



The selection is moved upwards, showing the new surfaces.

Slice Surface

This function is used to cut one or more surfaces across selected vertices.



Single surface with vertices selected



After Vertex->Slice Surface – now two surfaces



Surface _ surface is cut into two

Create Convex Surface/Object

This function uses a technique called 'convex hull' to create a new object that surrounds the vertices that are selected. This is very useful for joining complex objects together or for simplifying the creation of some complex shapes.



These two pictures show the function being used to join a cylinder to a cube.



Note that because this function makes a new object, the vertices are not shared with the old objects.

If the whole shape i.e the original objects plus the new part- is required to be smooth then the objects must be merged together (Object->Merge) and then have the duplicate vertices removed (Object->Optimize Vertices)

A second example uses a number of simple objects, which are 'shrink-wrapped' by this function. In this case we are creating the fuselage of an aircraft. The objects are ellipses and a single red box. Any AC3D objects can be used this way, either lines or polygons.



To get a more accurate outline, these shapes could have been made by placing background images of a real aircraft onto the views and building the shapes on top of those images.

After Surface->Create Convex Surface/Object menu function has been selected:



This picture shows the fuselage object created from the simple shapes. It has been dragged to the side of the original objects, which still remain in the scene. It's important to note that the hull created is

the hull created is 'convex'. This means that if there had been any vertices that were totally 'inside' the encompassing hull, the new hull object would not have any vertices created at those points.

This function will also create 2 dimensional convex hulls, provided all of the selected vertices lie on the same plane. If they are not, a 3d object will be created.

Create Ordered Surface

This function creates a surface using the individual vertices that are selected. The vertices should be selected in the correct order and in an anti-clockwise direction. This function works by creating a new surface and adding vertices in the order they were selected. If vertices are not selected in exactly the correct order, a bad surface (crossing edges or non-planar) may be created.

Create Quad

This function is used to create a four point, four sided surface from three selected vertices.



and new vertex selected

New vertex is positioned as desired

Create 2D Mesh

This function uses a technique called 'Delaunay Triangulation' to calculate triangles between a set of points. When this function is selected a plane is specified. This treats the points as 2D so that a mesh can be laid out over the points.



Example: here are a number of vertices

in the front window.

After Vertex->Create 2D Mesh->Front is applied.

To make vertices specifically for this function: create a line, placing each point at the desired location and select the line and Surface->Remove Surface Only. This removes the surface and leaves the vertices. Note that this function works convexly.

Boolean operations

AC3D's powerful Boolean functions take two objects and perform a volume-based operation between them.

The functions reside in the Object->Boolean main menu. Each function requires two objects to be selected.

To select two objects: first switch to Object (or Group) selection mode; one object is selected in the normal manner, then the second object can be selected by holding the shift key and clicking (or dragging over) another object.

In the following image a sphere has been positioned to overlap with a box. The subsequent sections illustrate the operations that can be performed from the intersection of these shapes.



Subtract

Using Object->Boolean->Subtract, the second object is 'subtracted' from the first as if they were solid shapes. This image illustrates the result of the subtraction.



Intersect

After Object->Boolean->Intersect, a new object is created from the overlapping solid volume between the two objects.



Union

Selecting Object->Boolean->Union creates a single object from the two objects. The overlapping portion is removed. Order of selection is unimportant.

As the function's result does not appear to be very different to the original objects, the result is best illustrated here in wireframe.





After Union - any internal surfaces have been removed.

Cut away

The Object->Boolean->Cut-Away function uses the second object to cut a 'solid' portion from the first. This function is similar to performing a Subtract and an Intersect at the same time.





The cut section is moved aside.

Knife

Unlike the previous Boolean functions, which require that both objects are 3D and closed (e.g. no open edges as in, for example, a tube), AC3D's two knife operations can use a 2D or open 3D object as the primary operand. In both functions the second object (which is used as the 'knife') must be a closed 3D object.



After the Knife. The appearance is the same as Cut Away but the result is a single object.



Viewing this In wireframe shows that the box surfaces have been sliced and no internal surfaces are created.

Knife and Cut Away

This function is similar to Knife except the original object is split into two objects along the cut edges.



The result appears to be the same as Knife but is actually two objects.



Here, the cut away part has been move aside. There are no internal surfaces.

Boolean examples

Cutting a round-ended channel in a cylindrical object







After **Object->Boolean->Subtract**, the channel has been cut.

A cylindrical object and an oval object.

The channel -cutting piece is moved to overlap the cylinder. The cylinder is selected by clicking and then the oval is selected by shift and clicking.

Cutting an aileron from a wing

In this case, we want to cut a solid shape from a wing and retain the cut piece. A box is positioned over the area of the wing that is to be cut out. The **Object->Boolean->Cut-Away** function is used.





Before Object->Boolean->Cut-Away.



This image shows the aileron moved away.

Cutting multiple windows from a fuselage



This image shows a hollow cylinder and three oval shapes. The three oval shapes have been merged together to form a single object (**Object->Merge**) so that they can be used in a single Boolean operation.



The ovals are moved into the large tube so that the objects overlap.



After **Object->Boolean->Knife-and-Cut-Away**, the pieces cut are in oval holes.

This image shows the model after the ovals have been moved away from the main tube object.

If **Object->Boolean->Knife** had been used, the window shapes would still be part of the main object.

Note that for the knife functions, the main object (first selected) does not need to be 3D and closed.



Cutting a solid object at an angle





This image shows a cylinder and a box. The box has been positioned at an angle over the end of the cylinder.

A wireframe view shows the end of the cylinder fully enclosed inside the box. Anything inside the box will be cut away from the cylinder.





This shows the result of selecting Object->Boolean- The cut piece has been moved >Cut-Away.



If Boolean->Object->Knife-Cut-Away is used, the object has been cut but is no longer solid

Hints and Tips

To perform successful Boolean operations:

- All objects should be three-dimensional and have no open edges: the object should appear 'solid'. The exception for this is the main object being used for one of the knife functions this may be open or 2D. The knife objects (the second selected object which is used to cut) must be 3D and closed.
- All surface normals should be facing outwards. This can be checked by displaying normals (3D and Orth menus, or pressing 'n' to toggle). When showing normals, the magenta lines should be facing away from the surface. If a surface normal line is not visible or appears as a magenta dot, the surface should be flipped with Surface->Flip-Normals.

Many triangles may be created if holes are created in a single polygon. It is often better to divide a single surface (Surface->Divide) before performing this type of Boolean operation.

To check overlapping objects before performing a Boolean function, it sometimes helps to view the model in wireframe – press the 'w' key or use the controls on the main Orth and 3D menus.

Subdivision Surfaces

Modeling with subdivision surfaces makes it easy to create smooth objects using simple polygon objects.



In AC3D, any polygon or line object can be subdivided. This includes objects containing ordinary (poly) surfaces and also lines and polylines. When an object is subdivided, the original geometry is used as a 'base' model. Any changes to this base model are instantly reflected in the smoothed subdivision.

Changing the subdivision level

The subdivision level can be quickly changed by using the Subdivide +/- items on the Object menu, or by using the toolbar buttons Subdiv +/-. Any whole or partly selected objects will have the subdivision level altered (subject to the maximum and minimum subdivision level)

0%	Subdiv + Subdiv -	
	W 0.94 H 0.88 D 0.91	
2	Comment Manuel Outlands 🕇	_

The subdivision level can also be altered by editing the object property from the Object Property Editor tool in the Tools menu.

Changing the subdivision level is not a permanent change to the geometry. AC3D still maintains the original object and any changes to this original object affect the subdivision.

All of the functions that work on normal surfaces are still functional. Adjusting the original surfaces directly affects the subdivided object.

Objects retain the subdivision property when AC3D files are saved. To export the model into another file format, keeping the smoothed subdivided shape, the objects can be transformed into full polygon objects by using Object->Commit Subdivision.

A setting in File->Settings defines a maximum number of surfaces for a subdivided object (Advanced->Subdivision maxsurfaces). If this maximum is exceeded when the subdivision level is changed, a message is shown and the subdivision will not proceed. The default value is chosen for average computers. For faster machines, the value can be increased.

Switching display of subdivisions

The display of subdivisions is easily changed by pressing the 'd' key. It is possible to have different settings for orth and 3d views e.g. orth views display the base (non-subdivided) model and the 3D view shows the full subdivided model.



Switching off the display of subdivisions in all views can be useful when working on large/detailed models, since AC3D will only calculate the subdivision when it is needed for display. Working without displaying subdivisions can therefore speed up interaction with the 3D model.

The main 3D menu has an option to simultaneously display the original base object as well as the subdivisions. This can sometimes be useful to see how the original object directly affects the subdivision.

Committing subdivisions

To apply the subdivision permanently, i.e. to create a new non-subdivided object with the same polygons as the subdivision, use Object->Commit Subdivision.

Examples

Subdivision works by dividing each surface and then smoothing the overall shape. An example – a simple box:

0 subdivision level

1 subdivision level





2 subdivision level



3 subdivision level



Note that the default surface type for a box is flat. Setting this to 'Smooth' and setting the object property for 'Crease angle' to 180 ensures that the object is fully smoothed. (Display of the surfaces has been switched off for this picture)







These images show a simple cup shape that was formed by using Object->Revolve on a line. The number of segments was set to 6. The image on the right shows this same object with subdivision level applied.

Hints and tips

Although any polygon in AC3D can be subdivided, subdivision works best with quads (four point/sided surfaces) since they divide symmetrically.



A cube is a good starting point for many models since each face can be extruded and the vertices moved to form other shapes, whilst retaining a single closed object with no holes. The block object is also a good base for building subdivided objects.

Using Extrude to add detail

Extrude is the best way to add extra detail to a subdivided object. These settings are recommended for extruding 3D subdivided shapes:



A simple way to add stronger defined edges to a model is to extrude with zero movement. This can be done by switching into extrude mode and simply clicking on the bounding box. The extrusion will be performed but no movement takes place. In the example here the left object is a cube with the top surface extruded. The right object is a copy of this object but with no subdivision level set – note that although it looks the same as a normal cube, there are actually extra surfaces around the edge of the top surface.



Display or hide subdivisions?

This image shows a cube with the top surface selected. Notice how the bounding box is not located directly over the selected surface (as it would be with a nonsubdivided object). This is normal, since the bounding box surrounds the original (non-subdivided) geometry.

Switching off the display of subdivisions (press 'd') shows why; the actual surface selected, in the original object is in a slightly different location because the subdivision causes the shape to change.

A similar effect can be seen in Vertex select-mode. Here, two vertices are selected – note how the selection shows around the area of the original vertices. This is because it is the original vertices that are affected; the subdivision is based on their positions.





Choosing the right subdivision level

Subdividing an object by one level increases the number of surfaces in that object by (a minimum of) four times and each subsequent subdivision increases this number by a factor of four. Each level of subdivision increases memory requirements and will have an effect on speed since there are many more polygons to be drawn and processed.

The number of vertices and surfaces in a subdivided object can be view from the Model Info tool on the Tools menu:



For general use, level 2 gives a smooth appearance to objects whilst keeping polygon counts lower. Obviously, machines with large amounts of memory, fast processors and fast graphics accelerators can work with larger models more easily.

Advanced users

The default maximum subdivision level in AC3D is 3. This can be increased in the advanced settings. You should be aware that any increase in subdivision levels increases the computational requirements.

Texturing



Each AC3D object can have one texture. A texture is set from the Object->Texture menu.

Setting a texture

Files of type:	Texture files (* tif, * tga,* ppm,* ipg,* bmp,* rgb,* 🔻	
	Texture files (".tif." toa." ppm." ipg." bmp." rab." rab.	
1 Size to	TIFF image files (*.tif) Targa picture files (*.tga)	
0 Rotate	JPEG picture files (*.jpg)	
100 Scale	Bitmap files (*.bmp) SGI rgb image files (*.rgb,*.rgba) GIF image files (*.git) Af files (*.r)	

Each AC3D object can have one texture applied to its surfaces.

After selecting an object (or objects), use the menu Object->Texture->Load Texture to set a texture.

AC3D loads a number of different picture file formats as textures. These include .gif, jpeg etc. To view which formats AC3D can load, see the load texture dialog.

Note that some export formats (or rather the programs that load the files) do not support all the texture file types that AC3D supports. You should ensure that you are using the correct format texture for the correct export file type e.g. .jpg or gif for VRML.

Changing the mapping

Texture coordinates determine how a texture is mapped onto the surfaces of an object. All AC3D objects have default texture coordinates applied to them when they are created. A cube for example has mapping set so that one instance of the texture will appear on each face.

Some external files have formats that do not contain texture coordinates and some AC3D operations may cause these coordinates to become disturbed; in these cases it is necessary to remap the texture coordinates.

Changing the texture repeat and offsets

The texture repeat and texture offset for an object can be modified in Object->Texture->Set texture repeat/offset. The texture repeat indicates the number of times the texture is to be fitted into that dimension.

Example: a cube with texture repeats set to 1, 1 (the default):



Object->Texture->settexture repeats/offsets and repeats set to 2, 2:

Texture rep Texture rep	satX2.0 < >		×
Texture offset ×		0.000	2 20 19 2
Texture offset Y	Ш	0.0000	9 20 49 20
I⊽ F	ealtime update	_	No.

The texture offset determines how far across the texture the mapping should start.

Texture repeat set to 1,1 and Texture offsets set to 0.5,0.5:



If more than one texture is required on a single object (e.g. a different image on each side of a cube), the object should be split up into parts (e.g. use Surface->Cut Away Object) and a different texture mapped on to each of the sub-objects.

Alternatively, it is more efficient to create a single texture image (i.e. a single picture file containing all the required images) and use AC3D's **Texture Coordinate Editor** tool to map parts of the object.

Tools

This section describes AC3D's integrated tools. Tools are accessed from the Tools menu. Other tools can be added to this menu via software plugins.

Model Information

This displays information about the current model.

Λ	Hodel Information	3
*	Group "WORLD", v 0, s 0, kids 1 Object "box", v 8, s 6, kids 0 * Total objects: 2 surfaces: 6 vertices: 8	
v	-	(F)
	Close Refresh	

This shows the information for a single cube. Note that the total number of objects shown is actually two. This is because the 'World' object is included in this count. The internal world object is the top-level container object. This window can remain visible whilst other work continues, but if any changes occur to the current AC3D model, the 'refresh' button must be pressed in order to update the displayed information.

Render

A Render		N N
Clutput file type:	Povlag •	
Dutput Bename:	ar.3dpovfile.prv	Browea
Render program	C VProgram Files/VPDV-Ray for Windows v3 B/bin/pvergine.ese	Browne .
Render parameters:	+UV +UL +A0.2 +FT32 %x	18
Result:		
	T Show Render button on toolber	
Rander		

This tool is used to start up an external renderer (such as a Raytracer like Povray) or other linked program. See the rendering section for more information on how this is configured.

Object Hierarchy

This window shows the structure of the current model but also allows control over the structure of the hierarchy.



Clicking on one of the items in the list can select or unselect objects. This selection is sensitive to the current select mode being used. In Group- select mode, for example, it is only possible to select top-level groups. To select individual objects, switch to Object -select mode (using the main AC3D control panel).

The eye icon shows/controls visibility (similar to Hide/Unhide on the main AC3D control panel). The padlock icon controls/shows if an object is locked.

A right click on an object item will reveal a popup menu:



This allows control over hiding, a more detailed properties viewer, editing object data and the option of moving an object to the head (start) or tail (end) of the children list.

Object Property Editor

Objects have properties that can be adjusted using the Object Property Editor. The crease angle and subdivision level can be adjusted by moving a slider and pressing a set button. Every AC3D object can have a URL (web link address) and text data attached to it. This is a string of text. This data is saved in the AC3D file, along with the object geometry information.

	Editing object properties	
Name URL Loc x Loc y Loc z Subdivision p Crease Object data test:	sphere 0.6 0.19 0.72 0 review 45 argle	Set Set
<u>+</u> 1	Close	2

Objects exported in VRML files will have a link generated around them if a URL is present, and Povray objects can include object data text at the end of each object description (allowing custom Povray commands to be added).

The Loc point defines the position of the centre of the object. This is the local origin of the object.

Texture Coordinate Editor



AC3D's integrated Texture Coordinate Editor (TCE) allows full control over the texture coordinates that are applied to all surfaces in AC3D objects.

To start the TCE select: Tools->Texture Coordinate Editor.

To edit the texture coordinates of an object, select a single object, or surfaces from a single object (in the main AC3D windows). The TCE runs in conjunction with the main AC3D program so it is possible to switch between the windows, selecting the surfaces and objects you wish to edit. Note that if a group object is selected (which has textured children) then nothing will appear in the TCE. In this case, switch to Object –select mode and select a single object.

The surfaces selected in AC3D will appear in the TCE according to their texture coordinates. All AC3D primitive objects (those created from the control panel) have default texture coordinates. For example:



Cylinder





It's important to realize that the pictures here represent the coordinates that are attached to each vertex reference in each surface and have no relation to the layout of the actual object vertices.

Note that the pictures above show the texture mapping for objects that have no textures applied. If there is a texture, it will be shown in the window.

Selecting and manipulating

When surfaces are selected in AC3D and the TCE is visible, the texture coordinates of those surfaces are all visualized. The TCE allows editing of all, or a subset of, the texture coordinates.

The TCE has two modes of selection: Surface and Vertex. In Surface-select mode, the texture coordinates are selected, moved and size by manipulating individual surfaces. Vertex- select mode allows individual texture coordinates to be manipulated.





Surface select mode

Vertex select mode

Manipulation in the TCE is similar to the main AC3D 2D views. After a selection is made, the green bounding box can be moved; the handles can be dragged to resize the selection and the selection can be extended and negated (shift left mouse, shift right mouse). The selection can also be rotated using the mouse. When the mouse pointer is over the edge of the bounding box, the pointer changes to indicate that if the left mouse button is dragged the selection will be rotated.



The Flip buttons mirror the selection either vertically or horizontally.



Flipped vertically



Flipped horizontally

Remapping the selection

- Remap
front (XY)
side (ZY)
top (XZ)
spherical

The 'Front', 'Side', 'Top' buttons 'project' the texture onto the surfaces in the specified axis. The bounding size of the selected surfaces determines the boundaries of the mapping. The 'spherical' button causes the texture coordinates to be 'wrapped' around selected surfaces.



It is possible that after starting the TCE and selecting an object the window appears blank. It is likely that the object has zero value texture coordinates e.g. each surface-vertex reference has 0.0, 0.0 as a coordinate. In a case like this, a 'Select all' in the TCE would reveal that all of the coordinates are set to 0, 0.

In this case, you will need to make sensible coordinates for your model, probably in groups. Do this by selecting a number of surfaces (from within AC3D) and using the remap buttons to assign a mapping to the texture coordinates. You can then reposition and size the surfaces in the TCE and map them onto a texture.

Replicator

AC3D Replicator	8	The Replicator allows multiple copies of the selection to be created. Each copy can be moved, rotated and
Copies Mode Translation (m) Rotation (degrees) Rotate about Scale	1 ⊕ Image: Construction Image: Construction 0 0 0 0 0 0 Image: Construction Image: Construction Image: Construction Image: Construction	scaled. The Replicator also allows objects to be extruded.

The replicator works by first duplicating (or extruding) the current selection. It then moves the new copy using the distances specified by Translation (X, Y, Z coordinates). If there is a rotation specified it rotates the object around the specified location. Finally if the scale fields are set to anything other than 1,1,1, the copy is scaled.

Examples:

Creating an array of 5 objects, 1 unit apart (in the X dimension)







Creating four copies, scaling each time:

AC3D Replicator				8
Copies	4	3		
Mode		G (Duplicate	C Extrude
Translation (m)	1	0	0	
Rotation (degrees)	0	0	0	
Rotate about	14	Dign	C Sele	ction (* 30 Curror
Scale	0.9	1.1	1.0	
1000	Go	1 0	lose	
1.1		1		

000



Extruding a 'horn' shape from a single ellipse.

A AC3D Replicator				8
Copies Mode	B	3 C 0	luplicate	🖗 Extrude
Translation (m)	1	0	0	
Rotation (degrees)	0	0	0	1
Rotate about	C	Origin .	· Sele	ction C 30 Cursor
Scale	1.4	1.4	1.4	
	Go		lose	



Creating a single step for a spiral staircase by extruding a rectangle



Use the replicator to duplicate the steps in a spiral pattern.

Create Text

The Create Text tool, which is to be found in the Tools menu, generates 2D and 3D objects from TrueType fonts.

A Create TrueType Text	. 3
Font path E:/WINDOWS/FO	INTS Browse
GOTHIC8I.TTF GOTHICI.TTF	4
HATTEN TTF mpact til L 10646 til latha til lucon til	بـ ب
Font Greek_1.ttl	
Text AC3D	
Object type	Parameters
C Outine	Font size 1
(* Sold	Extrude depth 0.1
C Extruded	Bevel depth 💷 🏅
C Beveled	Bevel angle \mid 🗇 🚊
and the second	Fort detail 5 🚖
Create	Fort detail

This image shows the same text in Outline, Solid, Extruded and Beveled type.



The font size specifies the maximum unit height of the text. The font detail (1 to 10) controls the number of vertices per letter. The greater the detail, the more surfaces and vertices will be in the resultant AC3D objects.

Align Objects

This allows objects to be repositioned relative to one object. Select a single object and then shift-select others. On pressing 'Align', the first object is used as the reference object.

Position 3D cursor



The 3d cursor specifies a position in 3D space. It is useful when creating objects since it specifies the 'missing' axis. For example, when a sphere is being drawn in the front window, the mouse movements specify the X and Y position of the sphere; the Z position comes from the location of the 3D cursor.

The default position of the 3D cursor is at the origin 0, 0, 0.

Many users find that they never need to adjust this, but it can be useful to change its position, when working on large models away from the origin.

Materials

The palette

The scrolling window of buttons near the bottom of the control panel represents the palette of colors/materials available. The default color for an object is palette entry 1 (usually white).

The colored buttons are pressed to change the material on the currently selected objects/surfaces. Setting the material of surfaces works in all selection modes, but for a surface to change color in Vertex mode it must have all vertices selected. Note that the color on the palette button represents the diffuse color for that material.

New palette buttons are appended to the list when a file containing extra materials is loaded.

When surfaces have a texture as well as a material, that material can affect the way the texture appears. To make a texture appear as the original colored image the surface color should be white.

To find the material index of an existing polygon, select that surface and the message at the bottom of the AC3D window will display the material number.

Editing Palette entries





Pressing the right mouse button on a palette button pops up a menu. The options are to edit a color, select all surfaces with that material or add a new material. A copy of the selected material will be added to the end of the list.

Pressing the colored button brings up a system color selection.

Pressing the '+' button next to an item expands the item so that the numeric values of the Red, Green and Blue components can be altered with sliders.

The material window allows various attributes of the material to be altered

Diffuse	This is essentially the main color of the material. The exact shade shown on a model depends on the amount of light available to the surface
Ambient	Ambient color works with the diffuse to affect the overall color of a surface, but is not sensitive to the amount of light on that surface.
Emissive	Setting this can make a surface appear to be giving off light. This may be used, for example, to give a light blue glow to a spaceship's engine. (No actual light is emitted from surfaces with an emissive color set.)
Specular	The specular quality defines the color and brightness of highlights. This works in conjunction with Shininess.
Shininess Transparency	A high value means that highlights will be smaller and less scattered across the surfaces. Transparency can be useful to for making a surface look like glass. Transparency is supported in the palette but for purposes of speed the surfaces are not sorted when they are rendered into the views.

If the 'real-time update' option is selected, any 3D view windows are redrawn every time a change is made to the material.

57

Loading and saving files

An AC3D file (usually named <something>.ac) is a text file describing the geometry of a model. AC3D files retain all available information about a model built with AC3D e.g. textures, surface settings, materials, object data etc. Other file formats exported by AC3D may not retain all of this information. Models should always be saved in this format to ensure that no detail is lost.

Developers can view a description of the file format on the AC3D website.

AC3D files are loaded by selecting File->Open. This will replace the current model. To load models in addition to the current model, use File->Merge.

A list of the most recently opened files appears on the File menu. Selecting one of these causes it to be loaded.

Importing other formats

See the File->Import menu for a list of file types that AC3D can import. Extra Import/Export plugins allow AC3D to handle more file formats. Check the AC3D website for details of additional plugins.

The following formats may be useful for importing your own model data.

Triangle files

Vector files

This is another simple format for importing 2D vector data. Each line should consist of a number of vertices followed by the same number x/y coordinate pairs e.g. $3\,0.5\,0.5\,2.5\,2.5\,10\,5$ This represents a line with 3 vertices (0.5, 0.5) (2.5, 2.5) (10, 5)

Exporting files

AC3D can generate output files for many different formats. Support for extra file formats can be added by installing additional AC3D plugins. See File->Export for a list of the output files supported. Several are mentioned here.

3D Studio (3ds)

3D studio files are used in 3D Studio Max 3D software. This is a long established binary format which is supported by a lot of third party software. Note that objects with > 1 material will be split into separate meshes within the 3DS file.

VRML 1

VRML is an ASCII geometry file specification used for web graphics. VRML files may be viewed from within any web browser that has an appropriate plugin installed e.g. Cortona

http://www.parallelgraphics.com/products/cortona/.

AC3D Object URLs (set from the object data dialog) are used so that objects will be selectable in the appropriate browser. The output of normals and textures can be switched on/off in the File->Settings window.

VRML 2

VRML 2 is a geometry description web file format which also allows animation and some other powerful constructs. See VRML 1 for a suitable browser plugin.

Output of normals and textures is switchable via Settings.

VRML2 Proto

This form of VRML2 output exports objects into a VRML prototype. This can be used when compositing larger models where each object may be stored in an individual file and a single file controls the locations of individual instances.

DIVE

Dive is a Virtual Reality system. The Dive generation will include the object data (if you have input any); this is usually TCL code. If an object has a URL then the object will be a dive gateway. See <u>http://www.sics.se/dive</u> for more info about the Dive VR system.

MASSIVE

Massive is a distributed VR tele-conferencing system written by Chris Greenhalgh at Nottingham University in the UK. It runs on SGI and Sun platforms. For more details, see:

http://www.crg.cs.nott.ac.uk/~csm/massive.html

RENDERMAN

These files are used in a raytracer. This allows detailed images with accurate lighting, shadows and reflections to be created from a 3D model. There are a number of Renderman- compatible renderers available. The eye viewpoint is defined by your view position in the primary 3D window (approx). Note that lines will not be output. Any polygons that need triangulating (breaking up into triangles) will be triangulated.

POV-Ray

POV-Ray is a very popular raytracer; see <u>www.povray.org</u> for more information. The eye viewpoint is defined by the view position in the 3D window. In Spin mode the viewpoint will be approximate; for a more accurate viewpoint position switch to walk-mode in the 3D window.

The color palette is output at the top of the file; each entry has the same number as the AC3D material. The properties can be altered easily to provide different surface types and textures (some #includes can be added at the top of the file to get external definitions). The light is output at the end of the file. The light's position is the same as the viewers. The POV-Ray output is based on triangles; lines will be ignored and polygons with more than three vertices will be triangulated automatically.

The Object data text, specified in Tools->Object Property Editor, can be used to attach information to objects which is then inserted into the POV-Ray file. 'Use object data in POV files' in the main AC3D File->Settings must be ticked so that this text is inserted into the file. A POV-Ray include command may be inserted in to the setting 'POV header' e.g. #include "glass.inc".

See the Rendering section for an example of using POV-Ray.

Triangle files

See loading triangle files for a description of this format. This format is very simple and is easy to parse.

Object Library



The object library is accessed from the File menu and can help organize and maintain a structured set of model component objects.

Objects may be added and removed from the library. For example, these 'components' may be electronic parts, kitchen units, molecule models etc.

Loading a single object from the library can be repeated to make multiple copies of the same object.

Note that the 3D position at which the object is saved will be its location when it is loaded again from the library.

To add an object to a library, select it and press "Store".

Take care when replacing objects, as the object that is currently selected in AC3D will overwrite the file stored on the library.

Rendering

The "Render" tool in the tools menu can be configured to automatically launch an external renderer. This allows generation of high-resolution images with shadows, reflections, transparency and other effects.

S210/04500		7
Output file type:	Povray	
Output filename:	ac3dpovfile.pov	
Render program:	C:\Program Files\POV-Ray for Windows v3.5\bin\pvengine.exe	1
Render parameters:	+UV +UL +A0.2 +FT32 %s	Ĩ
Result	GENERATING Poway: "ac3dportite.pov". EXCECUTING "exProgram Files/POV-Ray for Windows v3.5/bin/givengine.exe +UV +UL +A0.2 +F 123 ac3dportile.pov". 2224	and a second sec
Render	Obse	

The output file type is set from the 'Output file type' pull-down menu. The file types listed here are all of the file-types that AC3D can export (extra file-types may have been added using plugins).

The 'Output filename' specifies the name of a file that the model will be generated into.

The 'Render program' specifies the program that will start after the file is written.

The 'Render Parameters' are appended to the command line that it executed to start the render program. If a '%s' is specified in the render command, it will be replaced by the render filename.

A POV-Ray example

POV-Ray is a very popular ray-tracer - see www povray.org.



This example shows a very simple model consisting of a mesh, a sphere and a cube that has been divided a couple of times (with Surface->Divide), then had a Surface->Make Hole operation. There is also an extra light present in the model.

The sphere has had a pov texture specified using the Tools->Object Property Editor (the appearance of the object in AC3D will be unaffected by this):

AC3D Object Data	
Object name: sphere	URL:
	Str
texture (F_Glass10	1}
The settings in File	->Settings were:
POV header	#include "glass.inc"
🔽 Use object da	ta for POV files

Pressing the Render button in the Render Tool gives:



The Povray exporter supports bitmap-textured objects. Ensure that the formats of the texture picture files used are compatible with POV-Ray.

Appendix

3D Mouse support



AC3D supports 3Dconnexion's 3D navigation hardware. There are a number of different motion controllers available from 3Dconnexion, all are compatible with AC3D. A 3D mouse can be used in the AC3D's orthographic (2D) views and in 3D views (in both spin and walk modes).

In AC3D's Orth/2D views, a 3D mouse will pan (move left/right/up/down) and zoom. In a 3D view in spin-mode, the 3D mouse will act as if the selection is being handled (this is commonly called object-navigation in many CAD applications). In a 3D view in walk-mode, the 3D mouse is used to walk/fly around the scene as if the camera is being controlled (commonly called camera-mode navigation).

AC3D can be configured for both user preferences for zooming. Zooming can be performed either when the 3D mouse is pulled up/down or when it is pushed image chows a configuration dialog from a SpaceNavigator. In AC3D, this is

forwards/backwards. The following image shows a configuration dialog from a SpaceNavigator. In AC3D, this is shown when the right button on the SpaceNavigator device is clicked.

	Any Application - ac	v
ce configuration (App	Configuration Button Configuration A	Advanced Settings
bed		
Överal	Speed (Calbrate
Y	KONSTRUCT A	
an Disabia		
OTE LANGEORD		
A	1	_ 1
	879 0	S 12
	Cr°	
•	23	1

In this image, zooming is set for up/down on the SpaceNavigator.

There are two 3D mouse related settings in AC3D which can be altered. See menu File->Settings->Advanced:

3D mouse flip axis for walk mode 🔽

3D mouse flip axis for spin mode 🔽

These settings affect the way the SpaceNavigator controls rotation.

For up/down zoom direction, the rotating is done when the 3D mouse is twisted left/right. For forward/backward zooming, the rotation is controlled by tilting the 3D mouse left and right.

If zooming is set to up/down, as in the SpaceNavigator dialog image above (green arrows), these two settings should be left un-ticked. If the 3D mouse zoom is set for forward/backward (blue arrows), tick these settings.

The left device button on the space mouse is set to 'Fit'. This moves the display focus to the center of the current selection. An example; if you are navigating in spin-mode and wish to work on another object or part of an object,

change the selection and press the fit button. The right device button is set to bring up the settings dialog. Pressing this button again dismisses the dialog.

For more information on 3D connexion's devices, see <u>www.3d connexion.com</u>.

Plugins

Plugins add extra functionality and additional file format support to AC3D. Plugins files are usually named <something>.p and reside in the Plugins folder within the AC3D installation. Additional tcl files in the same folder may also provide user-interfaces and scripting for use with some plugins.

Plugins are automatically loaded when AC3D starts. The console displays the progress of loading plugins and will show any errors that occur. It is important that plugins are designed to run with the correct version of AC3D, or they may fail to load.



To find out more about the plugins that are currently installed, use Help->About Plugins.

Selecting each plugin line brings up a description and any associated instructions for the plugin.

Performance tips

Rendering more polygons takes more time. As larger and more detailed objects are edited, the rendering will take longer. Here are some tips to help edit larger models more effectively.

- Switch to wireframe viewing. This is faster to render than filled graphics.
- Use object hiding and locking. This reduces the graphics load.
- Edit in only one maximized view. This prevents all views from being updated every time a change is made.
- If surfaces can only be viewed from one side (e.g. they are outer surfaces of a closed object such as a box), set them to single-sided. This is slightly faster to draw.
- Switch on 'interactive-wireframe' in both the Orth and 3d menus. This temporarily sets the view to
 wireframe when being panned or zoomed using the mouse. Wireframe usually renders faster than filled
 polygons.
- The 'Interactive Wireframe' switches, located on the main Orth and 3D menus, will switch the views into wireframe for manipulations.
- When using surface-subdivision keep the subdivision preview level set to 1 or 2 when working on the object. Switching off the display of subdivisions will also speed up interaction.
- Use Object->Reduce to reduce the number of vertices/polygons in an object.

Key-presses

Key shortcuts for menu items are shown on the menus. Other keys can be used:

Key	Function
Cursor-keys	move view
Shift-Cursor	move view faster
Control-up	zoom in
Control-down	zoom out
Shift-Control-up	zoom in with larger step
Shift-Control-down	zoom out with larger step
Alt-Cursor	move background image
Alt-shift-cursor up/down	scale background image

Backspace/Delete	delete current selection
Space	maximize or minimize the current view

t	toggle textures
0	set select mode to OBJECT
v	set select mode to VERTEX
s	set select mode to SURFACE
m	set drag mode to MOVE
r	Set drag mode to ROTATE
е	set drag mode to EXTRUDE
f	fit selection to window
control-f	fit selection to all views
g	toggle grid
h	hide selected objects
z	zoom in
x	zoom out
Space	maximize/minimize view

Some of the keys for the 3D window have an equivalent menu item in the 3D menu.

In 3D views:	
Key	Function
w	wireframe/filled toggle
t	toggle textures
g	toggle 3d grid
f	fit to window/centre spin view around the selection
Space	maximize/minimize view

In the 3D window, the cursor-keys spin the model in 'spin-mode'. In Walk mode, they control the viewpoint in a similar way to 'Quake' and other games e.g. left, right, forward, back, alt-up/down move up/down, control-up/down tilt.

Preferences/settings

The settings in File->settings are saved automatically when you exit AC3D. This automatic saving can be switched off from the settings window. Settings must be saved with this set to 'off' for the change to be remembered.

Under Mac/Unix, the settings are saved to \$HOME/.ac3dprefs. Under Windows, they are saved to the user's home directory as ac3dprefs.txt.

Additional Information

Third-party plugins

There are a number of additional plugins that add extra functionality to AC3D. Some are supplied with AC3D and are described here, others are available via the AC3D forum pages – see the website for more information

Greeble

From SuperColdMilk, this excellent AC3D plugin makes it easy to add detail to your models.



Greeble is an AC3D plugin that adds greebles to existing geometry. Wikipedia defines a greeble thus: "...a small piece of detailing added to break up the surface of an object to add visual interest to a surface or object, particularly in movie special effects."

Greebles are placed in a separate object from the base object. Your base geometry is not modified.

The Greeble user-interface is accessible from the AC3D Tools menu.

A Greeble	
BEVEL	
🖂 Econing	
Lava hectercy(X	
E 2022 minimum no grans Lieves reasons to be oblive	
Esse mismum recent S	
Lava maximum ncent XI	· ÷
Ecolo civision frequency 8	E 1
1. 0. 101	
P Greebler	
finadale" e preneg X	
Minimum greebles per surface.	<u></u>
Maxil un greebles per culace	1 1
Greeble Hinimum height 3	7 🗄
Greeble maximum height 3	
Greeble 🔐 on size X	
Greeble maximum elee X	: <u>-</u>
Greeble rotation decrees	: =
Kandon seec	:1:::.
CI STOM	
Here is immercebles	
Hereiteren nichtereit	ດຮາກດ
Maintain e istem greeble te	bod
OFT DNC	
🔲 Greebles in reparate cost	
🔲 Real: me update:	
🖂 Cave setting: to greece [a	*=
Lieble greebied	
Circle greatics addr	ne -

There are many options, the parameters are described here.

Parameter	Usage
Beveling	If checked, bevels will be placed on selected surfaces prior to adding greebles. This is often used to get a discontinuous "raised floor" effect.
Bevel frequency %	The frequency with which bevels are applied to surfaces. For instance, a value of 75% means roughly 3/4 of the selected surfaces will be beveled.
Bevel minimum height % Bevel maximum height %	The minimum/maximum height that a bevel will be raised on a given surface (the actual value per surface is random). Beveling uses a formula that takes the area of the underlying surface into account. This number may exceed 100%.
Bevel minimum indent % Bevel maximum indent %	The distance from the edge of a surface that a bevel will start. Specify zero to have bevels at the very edge of a surface.
Bevel division frequency %	The frequency with which bevels will be split into 2, 3, or 4 separate bevels. If a bevel is split, the split between 2, 3, or 4 bevels is random. This feature only works on quads, not triangles.
Greebling	If checked, greebles will be placed either on the tops of bevels, or directly on the tops of surfaces where no bevels exist.
Greeble frequency %	The frequency with which greebles are applied to surfaces. For instance, a value of 75% means roughly 3/4 of the selected surfaces will be greebled.
Minimum greebles per surface Maximum greebles per surface	The number of greebles that will be applied to each surface.
Greeble minimum height % Greeble maximum height %	The raised height of each greeble. Greeble heights default to the surface area of the underlying surface. This number may exceed 100%.
Greeble minimum size % Greeble maximum size %	The size of each greeble as it is spread on the surface. 100% means the greeble will completely cover the surface.
Greeble rotation degrees	Greebles are randomly rotated when placed; this value dictates the increment (in degrees) which a greeble may be rotated, from 0 to 90.
Random seed	A seed for the randomizer used to determine greeble placement. Use a number here for consistent results between greeble runs on the same objects, or specify one (1) for a number based on the current date/time.
Use custom greebles	If checked, custom greebles will be located and used (if present). See the "Custom greebles" section below.
Use standard greebles with custom	If custom greebles are found and this box is checked, the custom greebles will be combined with standard greebles. If this box is not checked, standard greebles will not be used unless there were no custom greebles found.
Maintain custom greeble aspect	If checked, custom greebles will not be distorted to conform to the underlying surface. Use this for greebles where you wish to maintain their current width/depth/height aspect ratios. Note that this works best when placing greebles on relatively square/rectangular objects. When placing un-distorted greebles on triangles or skewed polygons, they may tend to gravitate toward the weighted center of the polygon rather than.
Greebles in separate objects	If checked, each greeble/bevel will be created in its own separate object. All greebles are then grouped into a single AC3D group. Note that this can cause significant slowdowns if you end up with thousands of greebles/bevels in separate objects.
Realtime updates	This feature provides you with an interactive preview, directly on your selected surfaces, of what your generated greeble will look like. The greebles will be updated as you tweak/change variables. While realtime preview is active, you will not be able to interact with your model. You may go in and out of realtime preview to rotate/scroll your model view to get a different perspective on the greeble-in-progress. Note that if you manually type values in fields, the realtime preview does not update - only when you use the numeric scrolls or the checkboxes does the preview update. Once you click the "Create greebles" button, the actual greebles are generated, and realtime preview is disabled.
Save settings to greeble Data	Enable this feature to write a summary of greeble settings to the newly created greeble object. Handy for seeing how you initially generated a greeble object. Use the AC3D object property window to see the contents of the Data field. Each textual setting is prefixed by "//", which should make this POV-Ray-safe.

Standard greebles

By default, there are 4 types of greebles, shown here.

These greebles are stretched, rotated and scaled in accordance with the underlying surface.



Custom greebles

Use custom greebles where the standard set does not meet your needs.

Custom greebles are merely AC3D objects. To make an object a custom greeble, edit the object's Data property (F9 in Object mode) and type "//CUSTOM_GREEBLE" (without the quotes) at the beginning of any line in the text box.

Make sure you type in all-caps as shown, and do not enter any spaces.

(NOTE: A future release may make this a friendlier process).

You may define as many custom greebles as you like. If you have a set that you like to use, you could save them to their own file and load that file into whichever document you'd like to use them.

Also, greebles should point "up" along the Y axis. Basically, the view of your greeble in the "top" view is the way the greeble will be applied to the target surfaces.

Once you have your custom greebles created, make sure the "Use custom greebles" checkbox is checked.

Below is an example using custom greebles. The cylinder and half-sphere have been defined as custom greebles. I have created a greebled cube with a mixture of custom and standard greebles.





Notice that the size of the custom greebles does not matter. It is copied and resized to a square area and then proportionally placed on the target object, so it doesn't keep any proportions you initially apply.

Texture coordinates are preserved on custom greebles, but the material used will be the same as the underlying surface onto which it is applied. Textures themselves are not applied to greebles by default (you must do that yourself).

For more information on the Greeble and other excellent AC3D plugins, see www.supercoldmilk.com.

© 2008 Inivis Limited

All rights reserved. No part of this publication may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording or storing in a retrieval system, or translated into any language in any form without the prior written permission of Inivis Ltd.

Software license

The software described in this document is furnished under a License Agreement, which is included with the product. This agreement specifies the permitted and prohibited uses of the product.

Licenses and trademarks

Inivis Itd., the Inivis logo, AC3D and the AC3D logo are trademarks of Inivis Itd. All other product names and any registered and unregistered trademarks mentioned in this manual are used for identification purposes only and remain the exclusive property of their respective owners.

Inivis

www.inivis.com

Last updated 4th July 2008